


Link Layer

- ❑ 5.1 Introduction and services
- ❑ 5.2 Error detection and correction
- ❑ 5.3 Multiple access protocols
- ❑ 5.4 Link-layer Addressing
- ❑ 5.5 Ethernet

Link Layer: Introduction

Some terminology:

- ❑ hosts and routers are **nodes**
- ❑ communication channels that connect adjacent nodes along communication path are **links**
 - wired links
 - wireless links
 - LANs
- ❑ layer-2 packet is a **frame**, encapsulates datagram



data-link layer has responsibility of transferring datagram from one node to adjacent node over a link

Link layer: context

- ❑ datagram transferred by different link protocols over different links:
 - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- ❑ each link protocol provides different services
 - e.g., may or may not provide rdt over link

transportation analogy

- ❑ trip from Princeton to Lausanne
 - limo: Princeton to JFK
 - plane: JFK to Geneva
 - train: Geneva to Lausanne
- ❑ tourist = **datagram**
- ❑ transport segment = **communication link**
- ❑ transportation mode = **link layer protocol**
- ❑ travel agent = **routing algorithm**

Link Layer Services

❑ *framing, link access:*

- encapsulate datagram into frame, adding header, trailer
- channel access if shared medium
- "MAC" addresses used in frame headers to identify source, dest
 - different from IP address!

❑ *reliable delivery between adjacent nodes*

- we learned how to do this already (chapter 3)!
- seldom used on low bit-error link (fiber, some twisted pair)
- wireless links: high error rates
 - Q: why both link-level and end-end reliability?

Link Layer Services (more)

❑ *flow control:*

- pacing between adjacent sending and receiving nodes

❑ *error detection:*

- errors caused by signal attenuation, noise.
- receiver detects presence of errors:
 - signals sender for retransmission or drops frame

❑ *error correction:*


- receiver identifies *and corrects* bit error(s) without resorting to retransmission

❑ *half-duplex and full-duplex*


- with half duplex, nodes at both ends of link can transmit, but not at same time

Where is the link layer implemented?

- ❑ in each and every host
- ❑ link layer implemented in "adaptor" (aka *network interface card* NIC)
 - Ethernet card, PCMCIA card, 802.11 card
 - implements link, physical layer
- ❑ attaches into host's system buses
- ❑ combination of hardware, software, firmware



Adaptors Communicating



□ sending side:

- encapsulates datagram in frame
- adds error checking bits, rdt, flow control, etc.

□ receiving side

- looks for errors, rdt, flow control, etc
- extracts datagram, passes to upper layer at receiving side

Link Layer


- ❑ 5.1 Introduction and services
- ❑ 5.2 Error detection and correction
- ❑ 5.3 Multiple access protocols
- ❑ 5.4 Link-layer Addressing
- ❑ 5.5 Ethernet

Error Detection

EDC= Error Detection and Correction bits (redundancy)

D = Data protected by error checking, may include header fields


- Error detection not 100% reliable!
 - protocol may miss some errors, but rarely
 - larger EDC field yields better detection and correction



Parity Checking


Single Bit Parity:

Detect single bit errors



Two Dimensional Bit Parity:

Detect *and correct* single bit errors



1	0	1	0	1
1	1	1	1	0
0	1	1	1	0
0	0	1	0	1

no errors

1	0	1	0	1
1	1	1	1	0
0	1	1	1	0
0	0	1	0	1

parity
error

*correctable
single bit error*

Internet checksum (review)

Goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer *only*)

Sender:


- ❑ treat segment contents as sequence of 16-bit integers
- ❑ checksum: addition (1's complement sum) of segment contents
- ❑ sender puts checksum value into UDP checksum field

Receiver:

- ❑ compute checksum of received segment
- ❑ check if computed checksum equals checksum field value:
 - NO - error detected
 - YES - no error detected.
But maybe errors nonetheless?

Checksumming: Cyclic Redundancy Check

- ❑ view data bits, **D**, as a binary number
- ❑ choose $r+1$ bit pattern (generator), **G**
- ❑ goal: choose r CRC bits, **R**, such that
 - $\langle D, R \rangle$ exactly divisible by G (modulo 2)
 - receiver knows G , divides $\langle D, R \rangle$ by G . If non-zero remainder: error detected!
 - can detect all burst errors less than $r+1$ bits
- ❑ widely used in practice (Ethernet, 802.11 WiFi, ATM)



$$D * 2^r \text{ XOR } R$$

mathematical formula

CRC Example

Want:

$$D \cdot 2^r \text{ XOR } R = nG$$


equivalently:

$$D \cdot 2^r = nG \text{ XOR } R$$

equivalently:

if we divide $D \cdot 2^r$ by G , want remainder R

$$R = \text{remainder} \left[\frac{D \cdot 2^r}{G} \right]$$




Link Layer

- ❑ 5.1 Introduction and services
- ❑ 5.2 Error detection and correction
- ❑ 5.3 Multiple access protocols
- ❑ 5.4 Link-layer Addressing
- ❑ 5.5 Ethernet

Multiple Access Links and Protocols

Two types of "links":


- ❑ point-to-point
 - PPP for dial-up access
 - point-to-point link between Ethernet switch and host
- ❑ **broadcast** (shared wire or medium)
 - old-fashioned Ethernet
 - upstream HFC
 - 802.11 wireless LAN



shared wire (e.g.,
cabled Ethernet)



shared RF
(e.g., 802.11 WiFi)



shared RF
(satellite)



humans at a
cocktail party
(shared air, acoustical)

Multiple Access protocols

- ❑ single shared broadcast channel
 - ❑ two or more simultaneous transmissions by nodes:
interference
 - **collision** if node receives two or more signals at the same time
- multiple access protocol*
- ❑ distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
 - ❑ communication about channel sharing must use channel itself!
 - no out-of-band channel for coordination

Ideal Multiple Access Protocol

Broadcast channel of rate R bps

1. when one node wants to transmit, it can send at rate R .
2. when M nodes want to transmit, each can send at average rate R/M
3. fully decentralized:
 - no special node to coordinate transmissions
 - no synchronization of clocks, slots
4. simple

MAC Protocols: a taxonomy

Three broad classes:

❑ Channel Partitioning

- divide channel into smaller “pieces” (time slots, frequency, code)
- allocate piece to node for exclusive use

❑ Random Access

- channel not divided, allow collisions
- “recover” from collisions


❑ “Taking turns”

- nodes take turns, but nodes with more to send can take longer turns

Channel Partitioning MAC protocols: TDMA

TDMA: time division multiple access


- ❑ access to channel in "rounds"
- ❑ each station gets fixed length slot (length = pkt trans time) in each round
- ❑ unused slots go idle
- ❑ example: 6-station LAN, 1,3,4 have pkt, slots 2,5,6 idle



Channel Partitioning MAC protocols: FDMA

FDMA: frequency division multiple access

- ❑ channel spectrum divided into frequency bands
- ❑ each station assigned fixed frequency band
- ❑ unused transmission time in frequency bands go idle
- ❑ example: 6-station LAN, 1,3,4 have pkt, frequency bands 2,5,6 idle



Random Access Protocols

- ❑ When node has packet to send
 - transmit at full channel data rate R .
 - no *a priori* coordination among nodes
- ❑ two or more transmitting nodes → “collision”,
- ❑ **random access MAC protocol** specifies:
 - how to detect collisions
 - how to recover from collisions (e.g., via delayed retransmissions)
- ❑ Examples of random access MAC protocols:
 - slotted ALOHA
 - ALOHA
 - CSMA, CSMA/CD, CSMA/CA

Slotted ALOHA


Assumptions:

- ❑ all frames same size
- ❑ time divided into equal size slots (time to transmit 1 frame)
- ❑ nodes start to transmit only slot beginning
- ❑ nodes are synchronized
- ❑ if 2 or more nodes transmit in slot, all nodes detect collision

Operation:

- ❑ when node obtains fresh frame, transmits in next slot
 - *if no collision*: node can send new frame in next slot
 - *if collision*: node retransmits frame in each subsequent slot with prob. p until success

Slotted ALOHA



Pros

- ❑ single active node can continuously transmit at full rate of channel
- ❑ highly decentralized: only slots in nodes need to be in sync
- ❑ simple

Cons

- ❑ collisions, wasting slots
- ❑ idle slots
- ❑ nodes may be able to detect collision in less than time to transmit packet
- ❑ clock synchronization

Slotted Aloha efficiency

Efficiency : long-run fraction of successful slots (many nodes, all with many frames to send)

- *suppose*: N nodes with many frames to send, each transmits in slot with probability p
- prob that given node has success in a slot = $p(1-p)^{N-1}$
- prob that *any* node has a success = $Np(1-p)^{N-1}$

- max efficiency: find p^* that maximizes $Np(1-p)^{N-1}$
- for many nodes, take limit of $Np^*(1-p^*)^{N-1}$ as N goes to infinity, gives:


$$\text{Max efficiency} = 1/e = .37$$

At best: channel used for useful transmissions 37% of time!



Pure (unslotted) ALOHA

- ❑ unslotted Aloha: simpler, no synchronization
- ❑ when frame first arrives
 - transmit immediately
- ❑ collision probability increases:
 - frame sent at t_0 collides with other frames sent in $[t_0-1, t_0+1]$



Pure Aloha efficiency

$P(\text{success by given node}) = P(\text{node transmits}) \cdot$

$P(\text{no other node transmits in } [p_0-1, p_0] \cdot$

$$P(\text{no other node transmits in } [p_0-1, p_0] \\ = p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$$

$$= p \cdot (1-p)^{2(N-1)}$$

... choosing optimum p and then letting $n \rightarrow \infty$...

$$= 1/(2e) = .18$$

even worse than slotted Aloha!

CSMA (Carrier Sense Multiple Access)

CSMA: listen before transmit:

If channel sensed idle: transmit entire frame

- ❑ If channel sensed busy, defer transmission

- ❑ human analogy: don't interrupt others!

CSMA collisions

collisions *can* still occur:


propagation delay means
two nodes may not hear
each other's transmission

collision:

entire packet transmission
time wasted

note:

role of distance & propagation
delay in determining collision
probability



CSMA/CD (Collision Detection)

CSMA/CD: carrier sensing, deferral as in CSMA

- collisions *detected* within short time
- colliding transmissions aborted, reducing channel wastage


□ collision detection:

- easy in wired LANs: measure signal strengths, compare transmitted, received signals
- difficult in wireless LANs: received signal strength overwhelmed by local transmission strength

□ human analogy: the polite conversationalist

CSMA/CD Network Size Restriction

To ensure that a packet is transmitted without a collision, a host must be able to detect a collision before it finishes transmitting a packet.



Events:

$t=0$: Host A starts transmitting a packet.
 $t=PROP--$: Just before the first bit reaches Host B, Host B senses the line to be idle and starts to transmit a packet.
 $t=PROP-$: A collision takes place near Host B.

$t=PROP$: Host B receives data whilst transmitting, and so detects the collision.
 $t=2PROP-$: Host A receives data whilst transmitting, and so detects the collision.

CSMA/CD Network Size Restriction

"To ensure that a packet is transmitted without a collision, a host must be able to detect a collision before it finishes transmitting a packet."

From example on previous slide we can see that for a Host to detect a collision before it finishes transmitting a packet, we require:

$$TRANSP > 2 \times PROP$$

In other words, there is a **minimum** length packet for CSMA/CD networks.

"Taking Turns" MAC protocols

channel partitioning MAC protocols:

- share channel *efficiently* and *fairly* at high load
- inefficient at low load: delay in channel access, $1/N$ bandwidth allocated even if only 1 active node!

Random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead


"taking turns" protocols

look for best of both worlds!

"Taking Turns" MAC protocols

Polling:


- ❑ master node
 - "invites" slave nodes to transmit in turn
- ❑ typically used with "dumb" slave devices
- ❑ concerns:
 - polling overhead
 - latency
 - single point of failure (master)



"Taking Turns" MAC protocols

Token passing:

- ❑ control **token** passed from one node to next sequentially.
- ❑ token message
- ❑ concerns:
 - token overhead
 - latency
 - single point of failure (token)



Summary of MAC protocols

- ❑ *channel partitioning*, by time, frequency or code
 - Time Division, Frequency Division
- ❑ *random access* (dynamic),
 - ALOHA, S-ALOHA, CSMA, CSMA/CD
 - carrier sensing: easy in some technologies (wire), hard in others (wireless)
 - CSMA/CD used in Ethernet
 - CSMA/CA used in 802.11
- ❑ *taking turns*
 - polling from central site, token passing
 - Bluetooth, FDDI, IBM Token Ring

Link Layer

- ❑ 5.1 Introduction and services
- ❑ 5.2 Error detection and correction
- ❑ 5.3 Multiple access protocols
- ❑ 5.4 Link-Layer Addressing
- ❑ 5.5 Ethernet
- ❑ 5.6 Link-layer switches
- ❑ 5.7 PPP
- ❑ 5.8 Link Virtualization: ATM, MPLS

MAC Addresses and ARP

□ 32-bit IP address:


- *network-layer* address
- used to get datagram to destination IP subnet

□ MAC (or LAN or physical or Ethernet) address:

- function: *get frame from one interface to another physically-connected interface (same network)*
- 48 bit MAC address (for most LANs)
 - burned in NIC ROM, also sometimes software settable

LAN Addresses and ARP

Each adapter on LAN has unique LAN address




LAN Address (more)

- ❑ MAC address allocation administered by IEEE
- ❑ manufacturer buys portion of MAC address space (to assure uniqueness)
- ❑ analogy:
 - (a) MAC address: like Social Security Number
 - (b) IP address: like postal address
- ❑ MAC flat address → portability
 - can move LAN card from one LAN to another
- ❑ IP hierarchical address NOT portable
 - address depends on IP subnet to which node is attached

ARP: Address Resolution Protocol

Question: how to determine MAC address of B knowing B's IP address?

- ❑ Each IP node (host, router) on LAN has **ARP** table
- ❑ ARP table: IP/MAC address mappings for some LAN nodes
 - < IP address; MAC address; TTL >
 - TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)




ARP protocol: Same LAN (network)

- ❑ A wants to send datagram to B, and B's MAC address not in A's ARP table.
- ❑ A **broadcasts** ARP query packet, containing B's IP address
 - dest MAC address = FF-FF-FF-FF-FF-FF
 - all machines on LAN receive ARP query
- ❑ B receives ARP packet, replies to A with its (B's) MAC address
 - frame sent to A's MAC address (unicast)
- ❑ A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
 - soft state: information that times out (goes away) unless refreshed
- ❑ ARP is "plug-and-play":
 - nodes create their ARP tables *without intervention from net administrator*

Addressing: routing to another LAN

walkthrough: **send datagram from A to B via R**

assume A knows B's IP address



- two ARP tables in router R, one for each IP network (LAN)

- ❑ A creates IP datagram with source A, destination B
- ❑ A uses ARP to get R's MAC address for 111.111.111.110
- ❑ A creates link-layer frame with R's MAC address as dest, frame contains A-to-B IP datagram
- ❑ A's NIC sends frame
- ❑ R's NIC receives frame
- ❑ R removes IP datagram from Ethernet frame, sees its destined to B
- ❑ R uses ARP to get B's MAC address
- ❑ R creates frame containing A-to-B IP datagram sends to B

This is a **really** important example - make sure you understand!

